

PAINT

User Guide (v10)

2025 June



Chyron PAINT • Version 10 • June 2025 • This document is distributed by Chyron in online (electronic) form only, and is not available for purchase in printed form.

This document is protected under copyright law. An authorized licensee of Chyron PAINT may reproduce this publication for the licensee's own use in learning how to use the software. This document may not be reproduced or distributed, in whole or in part, for commercial purposes, such as selling copies of this document or providing support or educational services to others.

Product specifications are subject to change without notice and this document does not represent a commitment or guarantee on the part of Chyron and associated parties. This product is subject to the terms and conditions of Chyron's software license agreement. The product may only be used in accordance with the license agreement.

Any third-party software mentioned, described or referenced in this guide is the property of its respective owner. Instructions and descriptions of third-party software are for informational purposes only, as related to Chyron products and does not imply ownership, authority or guarantee of any kind by Chyron and associated parties.

This document is supplied as a guide for Chyron PAINT. Reasonable care has been taken in preparing the information it contains. However, this document may contain omissions, technical inaccuracies, or typographical errors. Chyron and associated companies do not accept responsibility of any kind for customers' losses due to the use of this document. Product specifications are subject to change without notice.

Copyright © 2025 Chyron, ChyronHego Corp. and its licensors. All rights reserved.

Table of Contents

01: Introduction.....	5
Overview.....	5
Key Features of Paint 10.....	5
Getting Started.....	5
02: Clips and Playlists.....	8
Overview.....	8
Footage.....	8
Playback Options.....	9
Playlists.....	10
03: Clip UI.....	14
New User Interface.....	14
User Time.....	16
Clip Control.....	18
UI: Default skin.....	22
Changing the Skin.....	24
04: Clip Import and Export.....	25
Overview.....	25
Import.....	25
Export.....	28
Smart Import and Smart Export.....	31
Clip Publishing to Social Media.....	32
05: Production Playback.....	34
Playback speed timeline.....	35
Virtual jog.....	38
Presentation Window.....	38
Web Remote Control.....	39
Snapshots.....	39
Full-Frame Stings.....	40
Jump to Time of Day.....	41
06: Tools.....	42
Tools Administration Dialog.....	43
Groups.....	43
07: Tool Customization.....	45
Custom Tools.....	45
Tool Customization.....	45
Shadows.....	47
Lighting.....	48
Slow-mo and Pause Default Duration.....	49
Tool Profiles.....	49
In/Out Effects.....	50
Tool Presets.....	53
Drawing presets.....	54

08: Tool Property Bindings.....	55
Overview.....	55
Connecting to a Binding Point.....	55
Value Updates.....	56
Generic XML Data Binding.....	59
Binding to GSIS Data.....	60
Binding to Tracab Player Path.....	61
Opta's SDAPI Event Data.....	61
Controls.....	61
09: Formation Tool.....	62
Overview.....	62
Formations.....	62
Presets.....	64
Counter Setup.....	67
10: Importing Data.....	69
Tracab Data Import.....	69
Zebra NFL Data Import.....	70
11: 3D Pitch.....	71
Overview.....	71
3D Calibration Editor.....	71
Pitch Auto-Calibration.....	74
12: 2D Player Tracking.....	76
2D Player Tracking plugin.....	76
Player Auto-Tracking.....	77
13: Multi-Angle Telestration.....	79
Overview.....	79
Clip Group Editor.....	79
Visualization.....	81
14: Chroma Key.....	82
Overview.....	82
Chroma Key Editor.....	82
15: Keyframe Animation.....	85
Overview.....	85
Basics.....	85
Linked Keyframe Animations.....	86
Graphic Eraser.....	94
16: Sweep Calibration.....	95

01: Introduction

Guide Info:	Paint 10
	Original date: 2025 June

Overview

Paint 10 is the sports analysis tool. Paint allows you to record live video, import files, stream live video, and add graphics to all, with an easy-to-use UI and toolset.

Paint 10 comes with a comprehensive set of tools for visualizing different facets of your chosen sport, or for highlighting individual player performance. The tools range from simple tied to field freehand lines, to fully 3D arrows and an interactive formation tool for tactical presentation. The look and feel of all inserted objects can be totally customized using standard image editing software to make the built-in tool set capable of fitting your brand or production look-and-feel.

Paint's built-in disc recorder allows for easy ingest of footage, in up to 3 channels of HD and 1 channel of UHD. The disc recorder can be exchanged for, or complemented by, an EVS control interface. Let the EVS operator prepare the sequences for analysis and let the commentator control the play out. No more "roll the clip, please...".

Key Features of Paint 10

- Automatic Player Tracking (Soccer, Football)
- Automatic Pitch Calibration (Soccer, Football)
- Sweep Calibration (Soccer)
- Graphical styles
- Presentation Window
- Bulk Clips Import
- Speed and Distance Visualization
- Pitch Zone Tool
- Formation Tool Export
- Paint Playlist

Getting Started

When you load Paint 10, the UI is laid out to help you get going quickly. From the quick action toolbar to the tools, the timeline and playback, Paint is designed to make your life easier.



Color codes for the new UI (as shown in the image below)

- Red: Toolbars
- White: Preview
- Yellow: Common Panel
- Green: Clipbanks
- Purple: Minimized timeline
- Blue: Advanced options



Toolbar menu

This menu allows you to trigger some of the main functions of Paint 10.




From left to right across the two rows in the picture above:

- RMB to move GUI
- Open Admin menu
- Close application
- Open Formation tool
- Open Tools Admin

Admin menu

The Admin menu allows you to access various functions of Paint from data bindings, in and out effects and more, which are detailed further down this guide.

The Admin menu can also be accessed by RMB pressing on the clear icon in the control bar.



Operator mode

Operator mode shows UI elements in preview, like keyframe animation trail, keyframe buttons, production end or graphic eraser.

Enabled by default. Can be disabled via button in tool administration dialog.



For more info, a full explanation of the functionality contained inside Operator Mode can be found in the following sections: Player Auto Tracking; Formation Tool; Chromakey; Animations.

02: Clips and Playlists

Overview

The disk recorder captures incoming video. You can define several clips and recall them by a single click on the clip button. Keep in mind, there is a finite amount of space in the video disk. Once the footage is assigned to any clip, the recorder makes sure the footage is never overwritten. When the capacity of the video disk is reached, the recorder begins to overwrite the oldest footage, which is not assigned to any clip.


Footage

Short in and out

Clips are defined by Short IN and Short OUT points. When the Short IN and Short OUT points are set, the system automatically writes about 10 seconds before/after the Short IN/OUT points. These additional protected areas are referred to as Guard-bands.

Clip footage is write protected for all available camera angles.

Only the fields between Short IN and OUT are played when the clip is recalled.



Use JOG to reach the Guard-band areas.

It is possible to replace the Short IN/OUT by assigning new ones (incl. by value from the Guard-bands.)

Hard IN/OUT cannot be replaced by new ones.

Note: You may need to press and hold the IN/OUT buttons for a while (~2 seconds) to replace the IN/OUT points.

Clip acquiring

A new clip is defined when the Short IN/OUT points are set. You can define a clip in both Live and Recorder mode. The currently selected camera angle is stored to the clip and will be automatically selected when the clip is recalled (see Skin description to change preferred camera angle).

The workflow of clip acquisition and storing differs according to the skin in use. Please proceed to skin description for more information.

Clip playback

In the Clip Bank, when you press the clip button, Paint 10 loads the IN point of the clip and stops there. This also selects the preferred camera angle if the clip was created from a live input.


Press the play button. The clip is played at nominal speed and stops at the OUT point. When the play button is pressed and the clip is at the OUT point, playback starts from the beginning of the clip. The Spacebar is set as Play/Pause action to control the video playback.

You can play clips at several playback rates. You have buttons for playback with nominal speed and slow speed (1/3 of the nominal). Other rates can be reached using Jog/Shuttle wheel or you can assign any rate to the Jog/Shuttle buttons (See Config Editor, Keyboard configuration and Jog/Shuttle button assignment).

Each clip can carry its own chroma key setting. It is used during playback. If the chroma key is not stored with the clip, it is inherited from the Live camera where the clip is recorded.

Playback Options

Options modifying playback can be found under the Playback widget via a popup menu invoked by right click.



Clear on play

All (supported) drawings not saved in the clip are cleared when Play is triggered. Applied with request on Play at various play rates (incl. Slow play etc.). Clear on play is not applied on shuttle.

Individual tools can override the global value to ignore Clear on Play.

- Disabled by default.
- Individual tools need to be switched to support ClearOnPlay in the Advanced section of Properties.
- Global toggle "Clear On Play" needs to be switched on in the Play button context menu

Reload on replay

When clip playback reaches the end and Play is triggered again the clip is reloaded, resulting in all unsaved modifications (added/edited drawings etc.) to be cleared. Without the automatic reload the modifications are maintained until saved or a clip is loaded manually by the user.

Enabled by default. You can toggle Reload On Replay on or off by selecting it in the popup menu.

Looped playback

When Play is triggered normally the playback stops when the end of the clip is reached. By selecting Looped Playback the clip will be play repeatedly until playback is paused.


One time action. This action needs to be setup inside the advanced config of Paint's config editor.

Audio monitoring

Audio bars can be enabled in the config setup by setting AudioBars value to be true/ticked. The audio bars will then be overlayed to the right of the video.

Playlists

Paint has a built-in playlist function that can hold up to 9 stored playlists at once and it supports an infinite amount of clips in each playlist. The playlist is an additional licensed feature.



Creating playlists

To create a playlist, use the RMB on any clip inside the clip banks and use LMB on the + New playlist option.




Adding clips to playlists

To add a specific clip to a playlist use the RMB on desired clip inside the clip banks to add clip into selected playlist.




When a clip is added to a playlist an icon will appear on top of the clip to make it clear that clip is part of a playlist.



Editing a playlist

Playlist has multiple editing functions such as deleting individual clips from a playlist, reposition clips within a playlist, (6 dots icon), individual layout of clips and removing an entire playlist.



Playing a playlist

To cue and select a specific playlist press in the highlighted area and use the top play button to start the selected playlists playback.




Once the playlist is cued the remaining time of the entire playlist is shown next to the timeline.



Playlist floating messages

Paint playlist has additional floating messages inside the preview window for:



- Playlist # is cued
- Playlist # is played
- Playlist # is removed
- Clip (Name) was added to Playlist #

Playlist actions

Paint playlists have 4 actions mappable to keyboard shortcuts and the default settings are:

Action	Keyboard Shortcut
AddCurrentClipToPlaylistAction	Ctrl+A
DeletePlaylistAction	Ctrl+D
PlayPlaylistAction	Ctrl+P
SelectPlaylistAction	Shift+1-9
Next Clip	<
Previous Clip	>

Note: Playlist feature requires a license upgrade.

Mark Cue Points

Paint allows you to define cue point entries and then faster re-cue. There are 3 actions mappable to keyboard shortcuts or for example a Jog Shuttle device.



	Description
MarkCuePoint	Memorizes cue point based on record timecode of the Live input, even if the clip is playing.
LastCuePoint	Re-cues the system to the previous timecode relative to the timecode of the field displayed in the preview panel. Pressing again will re-cue to the previous cue etc.
NextCuePoint	Re-cues the system to the next timecode relative to the timecode of the field displayed in the preview panel. Pressing again will re-cue to the next cue etc.

03: Clip UI

New User Interface

The Paint user interface has been updated to provide a better user experience.



Clip creation

A new clip is created after the definition of in and out points. You can do that both in Live and Recorder mode. Then assign the clip to a button (are blinking at this moment). Unused buttons are in green. Red buttons are already assigned. Reassignment causes the original clip to be lost and its footage might become unlocked.

The In/Out points of the clip can be redefined, just press and hold the In/Out buttons until it blinks (~2 seconds).

Each clip remembers the camera which was selected at the time of clip creation. To redefine the camera, which is selected automatically with the clip, press and hold the camera button until it blinks (~2 seconds).

Clip playback

You can play clip to play at several playback rates. You have buttons for playback with nominal speed and slow speed. Other rates can be reached using the Jog/Shuttle wheel or you can assign any rate to the Jog/Shuttle buttons (See Config Editor, Jog/Shuttle button assignment).

During playback you can change between cameras (if they have been recorded).

Clip slow playback rate presets

You can change the playback rate of the button with slow speed with predefined playback rates. You can choose one of these speeds from the popup menu attached to this slow play button.



Playback rate presets are defined in the configuration file Default playback rates mapping:

```
<PlayRatePreset>
<PlayRate>25</PlayRate>
<PlayRate>33</PlayRate>
<PlayRate>33</PlayRate>
<PlayRate>50</PlayRate>
<PlayRate>66</PlayRate>
<PlayRate>75</PlayRate>
<PlayRatePreset>
```

Clip tools menu

The clip menu is available from the Tools button next to the clip buttons. Most of the menu items are also accessible from the popup menu invoked by right-clicking on a Clip button.

Tool	Description
	Edit chromakey: This is a global feature. See the Chromakey section.
	Rename* : Specify a name for each clip, which is shown on the clip button below bank identifier. Press the clip Tools button and choose the Rename action, limited to 15 characters.
	Delete : Removes the selected clip and might unlock footage.
	Copy : Duplicated the selected clip. As when you define a new clip, the clip buttons begin to blink. Define the button for the new clip.
	Swap : Changes the button for the selected clip. The clip buttons begin to blink. Select one. If the button is already assigned to any clip, these two clips swap their buttons. Otherwise, the clip is simply moved to the new position.
	Exit clip : Deselects the current clip. Currently playing footage remains the same. Helps define a new clip near an existing one, without having to jog back from the very end of the footage.
	Take Snapshot : Available when a clip is selected. Takes snapshot of current frame of the clip, including all graphics, and saves it to a file located in the Documents folder.

*Footnote: Rename

The rename dialog supports two modes:

- With the virtual keyboard – for usage on a touch screen, supports a limited character set
- Without the virtual keyboard – for usage on desktop computer

With keyboard



Without virtual keyboard



The rename dialog mode is controlled by element `VirtualKeyboardEnabled` in the `config.xml` file.

```
<Window>
<VirtualKeyboardEnabled value="1"/>
</Window>
```

If you want to rename more clips, there is no need to close this dialog. Just select another clip by pressing the clip button and update its name.

User Time

User time is an optional timecode generated in your computer. There is a simple control tool to set and adjust the time. For example, the user timecode can be used as a match time for football games. The current time is based on your computer time, which is recorded together with video.



Set up time adjustments

Press + or - to increment or decrement the time. Holding the button longer makes the adjusting faster.

Predefined values, like 00:00 reset the time to this value and starts counting. The preset values can be defined in configuration file.

You can Start/Stop counting the time.

Configuration

User Time settings can be configured at Config Editor's User Interface page. Following options are available:

- Enabled - enables or disables user time
- Auto Start - when enabled, user time starts automatically on application start. When disabled, user has to start the time manually.
- Time Value - time value when started automatically. Can be 0:0 or current system time.

The preset values are user configurable at Advanced page of the Config Editor. Locate the UserTime element:




```
<UserTime>
  <Enabled value="" />
  <PresetTime></PresetTime>
  <PresetTime></PresetTime>
  <PresetTime></PresetTime>
  <PresetTime></PresetTime>
</UserTime>
```

Each element <PresetTime> is one preset value.

The time format is hh:mm:ss, mm:ss or "daytime" for current time.

Clip Control

Interface

Interface	Description
	Clip banks
	Clip. Press to select the clip.
	(Red Square) Clip with saved drawings. The drawings will be loaded and replayed together with the clip.
	(Pink Square) Clip imported from ChyronHego Virtual Placement that contains data from TRACAB system. Or clip with imported TRACAB data. Or with Automatic player tracking applied.
	Selected clip. Press to rewind the clip.
	The position is not occupied by any clip.
	Free to assign new clip.
	Occupied. Current clip may be overwritten.
	Switch to live input.

	Camera switch. Press and hold for a few seconds to redefine camera associated with a clip.
No Genlock	Missing Genlock warning indicator.
	In point not used. Press to set In point.
	The current time is after the In point.
	In point. Mark the first frame of the clip
	Current time is before the In point. Press and hold for a few seconds to redefine the In point.
	Out point not used. Press to set Out point.
	The current time code is before the Out point. Press and hold for a few seconds to redefine the Out point.
	Out point. Mark the last frame of the clip
	Current time is after the Out point. Press and hold for a few seconds to redefine the Out point.
	Exit clip. Press to exit clip and return to record train.
	Play clip. Press to replay the clip if it was paused at the Out point.
	Slower playback. Press to replay the clip at a slower rate if it was paused at the Out point.
	Pause clip.
	Play backward clip.
	Fast Jog/Shuttle indicator. Press the leftmost Jog/Shuttle button to switch this option. It speeds up the shuttle up to 60x and jog 50x
	Clip tools.

06:07:09	Actual timecode in format HH:MM::SS.Frame. It must be enabled in the config.
-----------------	--

Clip buttons with clip thumbnail

The skin allows you to assign thumbnails to clip buttons. Cue the desired video frame within the clip, invoke popup on the clip button and pick Grab Thumbnail menu item. The current frame is grabbed and a thumbnail is created. You can re-grab the thumbnail anytime later or clear it by picking Clear Thumbnail from the popup menu on the button.




Timebar

There is a timebar just above the video area. It visualizes clip playback progress together with important playback changes in the clip.



- Green bar: Visualizes the position in the clip. You can hover on this bar to expose the yellow handle.
- Yellow handle: You can drag through the clip to jump to a different part of video.
- Orange dashed pattern: Shows slow motion region.
- Red block (bright, wide): Shows paused clip.
- Red block (dark, thin): Shows a pause which requires a user input to resume the playback.

Graphic UI	Description
CLIP 5	Clip Name: Inherits the name that you have added to the currently selected clip
◀▶	Shuttle Handle: Click and drag the handle left and right, in order to fast forward or backward through the selected clip.
Timeline	Show timeline: Opens the timeline.
Keyframe	Keyframe (white diamonds) jumps to selected keyframe

	Right click on a tool instance row and quickly delete it.
	Click anywhere in the timeline header (where the numbers are) to jump to that frame in a clip
	(Clip icon) Revert back to simple view.
	(Keyframe diamond with strikethrough) Show/hide keyframes.
	(Green bar) Click and drag on the start or end of a tool instance and drag it left or right, in order to extend or shorten the production length of the clip.
	Zoom in and out of the timeline.

Timeline

When you have added graphics to a clip, you can now view those graphics and their keyframes inside a new timeline.

To open the timeline:

1. Press the timeline button.
2. The timeline opens for the selected clip over the clip banks.



Each tool instance in the timeline allows you to select it, which will highlight it in the preview window, you can see in the example below, the column on the player is selected, whilst the other columns are dimmed down:



UI: Default skin

The default skins are primarily designed for presentation using large touchscreens, which exist in versions 7 of Paint.



Clips administration dialog



Open the Administration menu above the Clear button and select the Clips Administration menu item. The Clip administration dialog is shown next to the clip palette. Clips administration contains all existing clips.

Create a new clip

1. Press the New button in the controls panel.
2. Select the camera from which you'd like the clip to be created.
3. The playback is stopped and you can browse through the recorded footage to select In/Out points of the new clip.
4. You can define a thumbnail for any clip. Just browse to the desired video frame and press the "Grab Thumbnail" button. You can also change the clip name.

Change properties of an existing clip

Select the clip and change In/Out points, thumbnail, name.

Clip palette administration

Use Drag&Drop to move clips from Clips Administration to Clip palette and other way. Live camera inputs have their own icons. They can be presented in the Clip palette.



Remove all clips

Open the popup menu on the clip palette in the administration dialog and choose "Remove all clips" menu item. When the action is confirmed, all clips are removed and the disk space allocated for their footage is freed.

Changing the Skin

If you were provided with some other skins or you have your own, you can choose between them in the following two ways:

- Config Editor > General
 - The skin will be applied next time Paint is launched. Restart app to relaunch.)
- Main menu > Change Skin...
 - App restarts automatically as soon as you select another skin.




04: Clip Import and Export

Overview


Paint supports importing clips from EVS XT machines and video files in most common video formats. Paint is also capable of exporting recorded or previously imported clip back to LSM or to a video file.

Import



In the skin, open a context menu on the clip button, where the imported clip should be located.

1. Choose Import Clips.
2. Import dialog appears.
3. Source: Choose source of clips (File, EVS, etc.)
4. Match Video Format checkbox enables checking whether video format of clip and current Paint video format are same.
 - a. When enabled, Paint refuses to import incompatible clips.
 - b. When disabled, imported video is resampled to match current video resolution when possible.



To import a clip in the "default" skin,

1. Open Clips Administration and press the "Import" button.
2. This opens an import dialog. The clip will be imported to a new clip.

The import button will start the import process. Clip will be placed to available slots starting with the one chosen for the import.

Import dialog is closed and the progress of the import is indicated by a progress bar over the clip.



You can cue another import, it will start when the current process is finished.

Clip name will be automatically set to the imported clip ID.

Cancel the current import via the popup menu on the clip button or from the Tools menu.

EVS

- Import/Export from/to EVS XT is a licensed feature.
- In the Source selector choose one of the predefined EVS servers or browse the EVS network
- Write the clip ID to the import dialog. This is a LSM-ID known by EVS operator. For example 123A.
- Do not specify machine name nor playlist.

File

1. In the Source selector, choose File
2. Browse to the file in the File chooser.
3. When the Import source and Clip id are set, press the Import button (or press enter) to start the import.
4. Import dialog is closed and the progress of the import is indicated on the clip button.
5. You can cue another import, it will start when the current process is finished.
6. Clip name will be automatically set to the imported clip ID.
7. Cancel the current import via the popup menu on the clip button or from the Tools menu.



File clip import

Clips previously exported from Paint might contain:

- Chroma key settings
- User pause points (see Pause tool)

Non-flattened clips might also contain:

- Timeline (see Playback speed timeline)
- Tool drawings

Clips imported from Virtual Placement 7 might contain


- Chroma key settings
- Linked keyframe animations
- Tracab data (see Binding to Tracab player path).

In the instance where the clip contains such data, they are also imported and used later during playback. Drawings, timeline and pause points are fully editable after import.

File clip export

You can export a clip to a standalone video file, which can be later played in any video player. Graphics saved in the clip are rendered into the exported clip.

Right click on the clip and choose the Export menu item is available in the Clip Administration dialog.



Clip ID

File name for the exported clip. The destination folder is added automatically if not specified. File extension is added automatically according to selected Profile. Both Destination folders and file extensions can be set in Config.

Profile

You can have several export profiles defined (with different parameters for the output codec). You can switch the the profile here. Not all profiles can be used with video format you currently use. If you try to export a clip with profile not compatible with the current video format, then the export fails. This usually shows the error "Operation not permitted".

Flatten

When checked, all tool drawings stored in the clip are rendered into the exported footage.

When unchecked, clean video footage is exported. The drawings are exported in the form of clip metadata and stored within the exported file. 3rd party video players ignore the metadata and play only clean video. When a non-flattened clip is imported into the Paint, the drawings become available and are fully editable.

The clip can contain pause points made by the Pause tool which are unpause by pressing play during normal operation. This interaction during export is not possible, however you can set a predefined length of the pause in the Config editor, Clip Import/Export tab.

Metadata

When the destination format supports storing metadata (example: .mov), an exported clip can contain:

- Chroma key settings
- User pause points (see Pause tool)

Non-flattened clips also contain:

- Timeline (see Playback speed timeline)
- Tool drawings

This data is used again after the clip is imported back to Paint.

Codecs

You can choose from several predefined codecs. Some codecs DnxHD or ProRes are not present until a valid License is present.

NVIDIA H.264 encoder requires a Kepler-based Nvidia GPU or newer.

Motion JPEG


This codec is used in the built-in disk recorder. When you select MJPEG export profile for unflattened export, video data is copied into the destination file without any recompression in full quality. Unflattened MJPEG clips are intended to be imported into Paint again later.

Interlaced clips might not be playable in the third-party video players until they have full MJPEG support. We recommend, for example, VLC media player for playback.

Export

Export process

All user interaction and video output is disabled during export. You are informed of progress of the export and you can cancel the process.



Bulk file clip export



Bulk export allows you to export several clips into either a single file or individual files for each clip at once. The clips are exported in user-defined order (= order of selection).

To export clips in bulk first select the Bulk Export... option in any clips context menu. A dialog with all available clips grouped by banks will appear with all from the current bank preselected. You can alter the selection and order by clicking on the check boxes on the left of banks and clips.



In the next dialog you can choose the destination file (in case of export to one file) or folder (when exporting each clip separately - name is taken from the clip username) and export profile.

See the Profile chapter for more information about export profiles.




You will be informed about the total and current clip export progress during exporting.

Flatten

When exporting into one file, flattening of graphics is always turned on. Otherwise, you can select whether or not to flatten the individual clips in the second stage dialog by **Flatten** check box.

Note: Exception being clips from Formation Tool where unflatten export is not supported.




Smart Import and Smart Export

Smart import splitting


Imported clip can be automatically split into many representing individual instances defined in the metadata.

Currently supported formats:

- Sportscode (.xml)
- XOS (.xchange)



To use this you first need to specify the format of metadata in the Config Editor > Clip Import/Export. After that, when the Split Clip option is checked in the import clip dialog, Paint will look for specified metadata and then split the given clip accordingly. When no metadata is found an error message appears and the clip continues to import normally (as one).



Split clips can be exported individually or in bulk, combined with any other normal and/or split clips in any selected order. Relevant metadata will be preserved, normal clips will appear as time gaps.

Any operations applied to individual clips resulting in timing changes (example: applying a slow-mo or pause) will also be automatically applied during the export.

Smart export

Clips automatically split by metadata can be also easily exported simply switching to the Source clips view in the export clip dialog.

Here you can see only the automatically split clips grouped by individual imports.

Simply select a whole group, in our case MATCHTRACKER LONG THROWS, to export all relevant in the apparent order or pick individual clips in any order required.




Clip Publishing to Social Media

Clip Export to Social Media allows you to export clips to YouTube, Twitter, and Instagram either individually or all at once. It is an additionally licensed feature.

When exporting a clip, in the destination dropdown option, select Social Media. This will open the Publish to Social Media Dialogue box. It is only possible to export to an H.264 profile for Social Media.

You can select the checkbox for each Social Media platform you wish to publish to. Once you are logged in, you will remain logged in unless you log yourself out. Should you work on a shared computer, remember to log yourself out when you finish your session.



You can set the following parameters for the clip when you export it:

- Clip Name: This is the name that will appear on Social Media as its title.
- Visibility: PUBLIC, PRIVATE or UNLISTED.
- Description: This is the text description that will appear (usually below) the clip in Social Media platforms.

When you hit export, the clips will be exported to a local dmp folder and pushed to your platforms of choice. The export will be shown as a progress bar in the clip slot in the UI.

Note: Clip Publish to Social Media requires a license upgrade.


05: Production Playback

Production start/end

Non-animated graphics have an unlimited production length. You can set production start and end to a specific time.



Press the Production button in the lower left corner of the video preview. The Production end button is shown next to graphic elements. The buttons are shown for graphics that belong to the currently selected tool.




Controls

Control	Description
	Start is at current time/end is at current time. Press the Button to set the production to current time.
	Infinite production. Press to set production start/end to actual time.
	Production start is in the past/Production end is in the future (relatively to current time).
	Production start is in the future/Production end is in the past (relatively to current time).
	Production is disabled (you cannot set end while being before start).

Playback speed timeline

Buttons

Control	Button
	Pause / Edit Pause
	
	Jog Shuttle
	The pause points are rendered above the timeline. Pause point is rendered in yellow while current time equals to time of that pause point
	Slow-motion/Edit slow-motion
	
	Pause/slow-motion length
	Saves the timeline into the clip

Pause

Pause: The pause tool inserts pause blocks into the playback timeline of the clip.

Automatic pause

Automatic pause: Inserts pause block with a desired duration. Supported by Zoom Pan and Playback speed tools.

1. Select a clip.
2. Cue to the desired frame to begin your pause.
3. Press the Edit Pause button.
4. If no Pause is defined at the current time, a new Pause block is created.

5. Use the Jog/Shuttle to define pause length. You can see the actual length of the block on the timeline.
6. The pause block is rendered in red color on the timeline.
7. Press Edit Pause button again.
8. Press the Save button to save the timeline into the clip.

Manual pause

Insert pause point at a given time. Playback stops here and waits for user request to continue playing. Supported by the Pause tool.

1. Select a clip.
2. Cue to the desired pause beginning.
3. Press the Pause button. Pause point is created.
4. The pause points are rendered in the timeline. Pause point is rendered in yellow while current time equals to time of that pause point.
5. Press the Pause button while being on an existing pause point.
6. Press the Save button to save the timeline into the clip.

Slow motion

Inserts a slow motion block into the playback timeline of the clip. When the clip is played, the playback speed is changed in defined time range.

To define Slow motion:

1. Select a clip.
2. Cue to the desired Slow motion block beginning.
3. Press the Edit Slow motion button. If no Slow motion block is defined at the current time, a new Slow motion block is created.
4. Use Jog/Shuttle to define Slow motion length. You can see the actual length of the block on the timeline.
5. Press the Edit Slow motion button again.
6. Press the Save button to save the timeline into the clip.

Pause/slow-motion length

The length of the Pause/Slow motion blocks is rendered on the timeline.

- SS:FF
 - SS means seconds
 - FF means fields or frames,

Example: Depending on current video format, HD_1080I _ 50 the FF values are in the range 0..49.

Initial duration of pause

Initial duration (in seconds) of a newly created pause can be set in the configuration file:

```



<Timeline>
  <PauseDefaultDuration value="5"/>
</Timeline>

```

Distance text

Some tools support showing a text that displays distance between end points of the drawing. An example is 3D Arrow tool.


Distance text settings can be found at the Distance tab of tool properties. The text can be aligned to its parent tool in different ways that are controlled by TrackingType selector.

Rendering	Distance Text
	None: Distance text is rendered as an on-screen text. TextPosition property controls position of text on the screen, having [0,0] in the center and [1,1] in right upper corner of the screen.
	Shape aligned: Distance text is rendered as an object lying on the ground. TextPosition defines relative distance of the text, in meters, text from the center of measured distance line.
	Camera facing: Distance text is rendered as a 3D object standing on the pitch, rotating towards camera continuously. TextPosition defines relative distance of the text, in meters, text from the center of measured distance line.

To adjust how the distance value is presented to video, use TextFormat property. It is using float value formatting syntax similar to the one used in C or Java.

Examples
<ul style="list-style-type: none"> Using formatting string <code>%.2f</code> meters results in displaying distance with 2-digit precision: 6.28 meters. Use <code>DistanceValueType</code> to change units of distance measurement.

Virtual jog



The Virtual Jog control allows you to jog inside the interface rather than using any hardware. The control is composed from the outer wheel, which can be virtually rotated like usual jog wheel. Drag the virtual jog wheel to jog through the video footage.

The middle of the jog wheel contains a button to play/pause video playback. The state changes according to the actual state of the playback.

Mouse-less operation

The skin is designed to allow basic operations without the need of a mouse accessible from the touchscreen stand.

Action	Gesture
Open Clip Administration dialog	Hold finger in the Clip palette for few seconds.
Exit application	Hold finger on the Clear button for a few seconds.
Administration menu	Hold finger for few seconds on the Clear button.
Change tool property	Hold finger for few seconds on a tool button.

Presentation Window

Allows you to present the preview from the main Paint window on an external monitor or projector without showing the controls (only video and drawings will be shown).

To use this feature:

1. Run Paint with 2 or more monitors connected in extend mode.

2. The main display will be occupied by the main application windows and the "Toggle Presentation Window" button will appear.
3. Click on the button to activate/deactivate.

Activate	Deactivate	MonitorDevice = 0	MonitorDevice = 1

The behavior of presentation windows can be altered in config XML. By default is enabled without specified MonitorDevice.

```

<OutputWindow>
  <!-- enabled by default -->
  <Enabled value="1"/>


  <!-- (optional) 0-based system monitor index -->
  <MonitorDevice value="1"/>
</OutputWindow>

```

Web Remote Control

Paint supports remote control of the software via a browser page. A UI for video control and telestration, along with video preview is streamed to a browser page to allow users to control clip selection and playback, telestrate, and use the formation tool remotely.

- Mac/iPad requires Safari 13 on MacOS and iPadOS (or later)
- Windows/Android requires Chrome browser



Note: Web Remote Control requires a license upgrade.

Snapshots

You can take a snapshot of the current video frame including all graphics and save it to a file. There's user action for this named "TakeScreenshot".

Parameters of the snapshot can be configured in the config editor. The Screenshot element can have following sub-elements:

Sub-element	Description
ImageFormat	Format of the image. Supported are "jpg", "png", "bmp". Default is "bmp".
NamePrefix	Name prefix of the image file. When empty, name of the clip is used if defined. Otherwise "PaintSnapshot" is used
Directory	The directory for storing snapshots. Empty will default to the Documents directory.

Full-Frame Stings

This concept allows you to create full-frame graphics that can be automatically added to the start of each clip. This is targeted to users who would like to either precede the clips with graphical info or sponsors graphics. The stings are in .gtc file format.

Assumptions

- The sting will always be positioned to fill the screen. So if a sting is made smaller than screen resolution, it will be resized to match the output resolution.
- The sting will be played at the output frame rate.
- The sting is not moveable by the user.
- The sting will be played at the start of the clip.
- The sting will be visible only when Play is pressed. It stays hidden during jogging etc.
- Stings must be enabled in the Config editor.

Workflow


Create a GTC clip using ChyronHego Clip Convertor available at the Download area. Follow instructions for .gtc clip creation in the User guide of the Clip Convertor. Resolution and frame rate should match the video output.

Copy the .gtc clip into the Stings folder. By default is the folder is located at:

- **MS Windows** → Documents/Paint10/Stings
- **OS X** → /Library/Application Support/ChyronHego/Paint/Tools/Stings

Run Paint, pick 'Stings...' item from the popup menu on the Clear button to open Stings editor. Here you can assign **Clip playback delay** to each of the stings. The sting starts playing when Play is pressed and video playback is delayed by this value [in Video fields]. This allows the sting to be fully played before the clip starts.

Select a clip to use. Click the Sting widget and pick one of the stings from the drop-down menu. Picking 'none' item will cause sting removal from the clip and reverting Playback delay. All changes of sting assignments to the clips are saved automatically.




Re-cue and play the clip to see the result.

Jump to Time of Day

This function allows you to jump back in the record train to a point specified by time of day. The function is available by pressing on the time of day time in the skin. The function is not available when a clip is selected.

Specify the time to jump to the next dialog. Keep in mind that no footage may be available for given time. The footage might have been overwritten at that given time or the application might not have been running at all.



06: Tools

Overview

There are a large set of predefined tools available after installation.

The application window contains toolbars, where you can place the tools you want to use. Tools can be added or removed in run-time.



Control	Description
	Saves current drawing to currently selected clip. The drawing will be loaded again when the clip is selected.
	Undo. Removes the last tool placed in the preview window.
	Clear all the drawings. To open the Administration menu:

Tools Administration Dialog

1. Open the Administration menu on the Clear button
2. Select the “Tools Administration” item, or press the Tools Admin icon.
3. The dialog can be closed by pressing the Clear button.

The Tool Administration dialog has two tabs:

- Default tab contains all predefined tools coming with the Paint.
- Custom tab contains customized tools. Drag and drop tools here to save them.



Add tool to the toolbar

Open the Tool administration dialog. Drag a tool from one of the tabs and drop it into the toolbar.

Remove tool from the toolbar

Open the Tool administration dialog. Drag a tool the opposite direction back and drop it into the default tab of the administration dialog.

Groups

It is possible to group tools, which will be represented by one tool, but you can quickly change to another tool from the group.

Create group

1. Open the Tool Administration dialog.
2. Drag a tool from the Tool Administration dialog or the toolbar and drop it on an existing tool (drop location is middle part of the Tool button.).
3. A group is created and expanded.



Expand group

There's a user gesture to expand the group. The gesture depends on tool layout:

Tools placement	Default expand group gesture
Bottom	Drag up
Left	Drag right
Right	Drag left
Top	Drag down

Group buttons are marked with a small group symbol in the corner of the button. Tools in each group are numbered for better orientation.

Remove tool from group

1. Open the Tool administration dialog.
2. Expand the group.
3. Now drag the tool and drop it into the:
 - a. Default tab of the administration dialog to remove the tool
 - b. Custom tab of the administration dialog to save the tool for later use
 - c. Toolbar to make it permanently visible in the Toolbar

Add tool to existing group

1. Open the Tool administration dialog.
2. Drag a tool from the Tool administration dialog or the toolbar and drop the tool in the middle part of a group button (as described in the Create Group paragraph).
3. The tool is appended to the group.

During drag, park the cursor in the middle part of the group button for a while (~2 seconds), it makes the group expand. Then you place the tool at the desired position.

Expand the destination group. Drag the cursor and place it at the desired position.

Change the active tool in a group

1. Open the group.
2. Select another tool.
3. The group is automatically closed and the tool is ready to use.

07: Tool Customization

Custom Tools

The tools come ready to use. Most properties of the tool can be customized in run-time if needed. Only the edited tool is changed. When the tool is removed, all changes are lost.

Tools can be customized and saved for later use. All customized tools are available in the Custom tab of the Tool administration dialog. Tools in the Custom tab and in the Toolbar are independent of one another. Changing properties of a tool in the Toolbar doesn't affect tools in the Custom tab and vice versa.

Create a custom tool

Drag a tool from either the default tab of administration dialog or from the Toolbar and drop it in the custom tab. The new tool can be renamed by pressing Rename in the popup menu of the tool or by pressing F2.

Clone custom tool

Drag the tool from the custom tab of administration dialog and drop it back to the same tab while holding the Ctrl key.

Remove custom tool

Drag a tool from the custom tab and drop it to the default tab.

Tool Customization

Open the popup menu for the tool (right click or touch and hold for about 2 seconds) and select one of the following.

- Tool tracking
- Tool keying

1. Tool tracking

Paint tools can use two tracking types:

- No tracking: Graphics drawn keep their position on the screen
- Motion tracking: Graphics move together with the background video, as though it is part of the scene.

Different tools support different sets of tracking modes. If more than a single tracking type is supported, it is possible to choose the actual tracking type using the tool popup menu (click RMB on the tool button or long touch).

2. Tool keying

Paint tools can be keyed. Keying can be changed during the run of the application. The menu is available when the given tool supports both keying modes.

When using keyed tools, make sure the chroma key is properly set.


- **On** = The tool is keyed. If adaptive keying is supported by the tool (all except freehand strokes), keying is not used when graphics are placed to an area, where the key is bad or empty.
- **Off** = Tool is not keyed.

3. Tool properties

Here you can find the rest of the editable properties of the tool. All items have tooltips with a short description. Properties for each tool are described in the Tool Reference chapter.

All properties are initialized with their default values. The bold name of the property indicates that the value of the property differs from the default value (has been changed).

Bold property category (tab) indicates it contains properties with non-default value.



Shadows


Paint tools are capable of casting shadows (with some exceptions like Offside, Pause etc.). Shadows are rendered when both global and per-tool switch is enabled. Shadows are enabled on most tools and disabled by global switch by default.

You can enable/disable shadows on the tools in the Tool Properties dialog by switching the value of ShadowEnabled property.

Global shadow properties

The dialog with shadows can be opened from the Administration menu by the Settings menu item. The settings are global and applied on all drawings. The settings are stored within the current profile (see Tool Profiles).

Note: High values of Blur radius might cause performance drop and are not recommended.




Global shadow property descriptions

Property	Description
Enabled	Enables/disables shadow rendering. The shadow is rendered when both this and ShadowEnabled on Tool is ON.
UseLightDirection	If checked, light direction will be used to calculate shadow position. See Lighting description. Applies to 3D tools only.
Blur radius	Controls level of blurring. Lower values cause the shadow to look sharper.
Intensity	Intensity of the shadow. Lower values cause the shadow to be less visible.
Angle	Angle in degrees of the cast shadow. With 0 the shadow is cast in the 12 o'clock direction, 180 causes the shadow to be cast in the 6 o'clock direction.
Distance	Distance of the shadow from the drawing.

Discolor effects

Some tools use a discolor effect for the background (Zoom tool, CutOut tool, PitchFocus Tool...). You can change the parameters of the discolor filter in the Discolor tab of the Settings dialog. Open the Administration menu menu on the Clear button and pick the 'Render effects' menu item.



Effect	Description
Contrast	Contrast of the background.
Brightness	Brightness of the background.
BWFactor	Black/White factor. 1 means fully B&W, 0 means that no B&W effect is applied.
Blur	Amount of blur applied to the background. 0 means none, 10 means total blur.
Color	Allows you to set the color applied to the background.

Lighting


Defines one global source of light, which allows 3D tools to be correctly shaded, cast shadow and reflect light.

	Description
Angle	Angle in degrees of the light. With 0 the shadow is cast in the 12 o'clock direction, 180 causes the shadow to be cast in the 6 o'clock direction.
Altitude	Altitude of the light in degrees. 0 means 'on the surface', 90 means infinitely high.
Env. Texture	You might define an environmental texture, to use for faking reflections and more realistic results. Lighting without any environmental texture causes poor visual results.



Slow-mo and Pause Default Duration

Each time you press a button to create a pause or slo-mo sequence.



Tool Profiles

Profile are sets of tools displayed in the toolbar. You can have several predefined profiles and change the actual profile in one step.



Administration menu contains the following actions:

- Open profile – Menu with existing profiles shows up.
- New profile – New empty profile with a user-specified name is created.
- Save profile as – Current profile is saved under user-specified name.

All changes you make to the current profile (add/remove tools) are automatically saved.

Toolbar capacity might be lower than the number of tools defined in the profile. In this instance a warning dialog is open with the following choices:

- Ignore – Tools that don't fit the toolbar are removed. This change is not saved into the profile until the toolbar is altered manually.
- Create copy – Creates and automatically selects a copy of current profile, tools that don't fit into the toolbar are removed.

Default tool

Default tool is automatically selected when the application is started and each time the Clear button is pressed.

This tool might have different button icon to easily identify which tool is actually default (depends on current skin).

- Set a tool to be Default by checking the Default tool item in the popup menu for a tool.
- Unset a tool to be Default by unchecking the Default tool item in the popup menu for actually default tool.




In/Out Effects

Special effects can be added when graphics start or finish their production length.

Managing effects

Effects are managed in the Effects dialog that can be opened from the administration dialog (right mouse button on the Clear button) and selecting In/Out Effects.



The list on the left side contains all the effects. It has these columns:

- Name – name of the effect
- Style – animation style of the effect
- Clip – whether the effect it has an associated clip
- Used – whether this effect is used by a tool in the current profile

The dialog allows you to create a new effect, clone existing, remove existing. The rename function is opened by double clicking on the effect or by pressing F2.

Parameters of the selected effect can be set in the panel on the right side. Default effects can not be changed. "Default Effect" is set to a tool that is added to the toolbar.

Using effects

Open a tool property editor, switch to the "In/Out effects" tab and select an effect from the combo boxes.



Value "-none-" means that no effect will be applied. An exclamation mark next to the combo box indicates that the effect animation style is not supported by the current tool. It means that the effect animation will not be performed. If a clip is set, it is always played.

The cog button on the right side opens a popup menu with additional commands. The effects dialog will be shown after choosing any of the options.



Parameters of effects

Animation	
Parameter	Description
Style	NONE – no animation is used FADE – opacity animation. DRAW – stretching or shortening. The final result depends on a tool. The tools define the look of the effect. For example freehand and arrow tools can have an effect where the stroke grows or shrinks. SCALE - size animation.
Duration	Duration of animation in frames.
Delay	Delay of the animation related to begin/end. It allows you to play clip before running the animation.
Sequential	A part of a graphic is animated right after the animation of the previous part is finished. Is used only when the placed graphic is made from parts.
Reverse	Flips direction of the Draw animation. Only visible when Style is set to Draw.
Pivot	Pivot of Scale animation defined in bounding box of graphic. [0,0] = bottom left corner, [1,1] = top left corner. Only visible when Style is set to Scale.

Clip

	Description
File	Path to gtc clip file.
Position	CENTER – clip is placed in center of bounding box computed from graphic. START – clip is placed at the first point of a stroke. Used only when graphic contains a stroke. END – a clip is placed at last point of a stroke. Used only when a graphic contains a stroke.
Mode	FOREGROUND – chroma key off. BACKGROUND – chroma key on.
Blend mode	MULT – Multiplicative blending mode. ADD – Additive blending mode.

Opacity	Opacity of a clip.
Size	Scale of a clip.

Using effects with text

When using any tools with a text input and .gtc background (e. g. Tag tool), the text animates in with the first frame of the background, and animates out with the final frame of the background.

It is often required to control fade in/out of the text since the .gtc might already contain a specially rendered in/out effects.


You can set the offsets in the Tool Property editor, Text tab altering values of these properties:

Fade Type	Description
TextFadeInDelay	Defines the delay between production start of the background and fade-in of the text (e.g. setting a value of 10 means that the text starts fade-in with 10 frame of the .gtc background).
TextFadeOutPreroll	Defines a pre roll of the production end of the text (e. g. having .gtc clip 100 frames long and setting value of 10 means that the text starts to fade-out with 90 frame of the clip).

Tool Presets

Preset settings


Tools can have a number of back-end presets built inside it. These presets have different settings such as colors, settings for animations and files. You can access them in the tool context menu by right clicking it. Currently applied preset(s) will be marked with a checkmark.



Fast preset selection

Presets can have fast selection enabled. These presets won't be shown in the Presets context menu mentioned above but instead each time the user clicks into the preview to create a drawing,

A popup menu with available preset options will be shown. He then selects one to apply it before the drawing is created or chooses the <Unchanged> option to simply use the tool as is.




Drawing presets

Since 9.7, presets can be applied for a drawing after it was placed in the preview. You can achieve that by right clicking on the drawing in the timeline. If there are any available presets for the drawing, the menu will contain item Presets with the same presets found in the context menu of the tool that was used to create the drawing (parent tool). Presets with checkmarks are currently applied for the drawing.

It can happen that a Presets menu item isn't present either because . . .

- the drawing is from older versions than 9.7
- the parent tool doesn't have any presets
- the parent tool cannot be found in the toolbar



08: Tool Property Bindings


Overview

This feature allows you to change Tool settings from third-party applications in runtime. Simply connect the chosen Tool properties to appropriate binding points and feed the binding points with new values.



Connecting to a Binding Point

Open the Tool properties editor from the popup menu available on the tool. Open the popup menu for property to bind and choose 'Binding...' menu item. Fill in the Binding name in the dialog. The name is pre-filled with the name of the existing binding or name of the property. You can fill in any name you want or you can press the browse button (labeled with '...') and choose from a list of available binding points. The dialog contains binding points defined by the user and predefined binding names provided by external plugins.



All properties bound to one binding point are fed with the same values (example: you can change the color of several tools at once).

Properties already bound to a binding point have their name and category visualized in blue color in the Tool property editor. You can clear the Binding (start using the value from the editors) from the popup menu of a Tool property.

Value Updates

Binding points can be fed with new values while the application is running. Clients responsible with feeding values to the binding points can send a single value or list of values to each binding point.

Binding point with a single value

A Binding point has only one possible value. All properties bound to this point start using this value immediately.

Binding point with multiple values

A Binding point has several possible values (e. g. list of player names). Properties start using the value at the same index as before any update. It starts to use the last value when the index is out of range of updated values.

Set up current value

You can change the current value when multiple values are available. Invoke popup menu for a tool and go to the Bindings menu where you can find names of bound Tool properties. You can select one of the values in the next submenu. The value is used until another value is selected or the binding point is fed with different values.



Fast selection of current value

There is another way to set property value for a drawing just in time of drawing creation. You can mark one property with the 'Fast selection' flag which is available in the popup menu for a property.

See the "Connecting to a Binding point" section for more info.

Each time you click into the preview to create a drawing, a popup menu with available values for the property is shown. Pick one of choices from the menu.

A drawing is created with the binding value applied at the point you clicked into the video.



Updates from a file

This is the easiest way of sending value updates from third-party applications. Paint declares the names of all existing Binding points to a file accessible for third-party applications. Binding names are serialized to XML file and saved to names.xml located at:

Operating System	Location
Microsoft Windows	Documents/Paint10/Bindings
Mac OS X	Library/Application Support/ChyronHego/Paint/Tools/Bindings/

MS Windows

The format is as follows:

```
<Bindings version="1">
  <Binding name="UserSpecifiedName"/>
  <Binding name="UserSpecifiedName2"/>
  ...
</Bindings>
```

Delivering update

Application waits for value updates when there's at least one active Binding point. Paint watches for changes of the value update file and when a change is detected, the whole file is reloaded.

The file must be named values.xml located at the same folder as names.xml. The format is as shown below. Binding point that should be fed with multiple values just repeat the Value element with different text content of the element.

Optionally you can define user friendly name of the value displayed in the Bindings popup menu. This is done by adding heading attribute to the Value element. When the attribute is not present, the value itself is displayed in the Bindings popup.

```

<Bindings>
  <Binding name="Color"> <!-- Name of the binding point -->
    <Value heading="Red">[1,0,0,1]</Value>
    <Value heading="Yellow">[1,1,0,1]</Value>
  </Binding>
  <Binding name="PlayerName">
    <Value>Messi</Value>
    <Value>Ronaldo</Value>
    <Value>Rodriguez</Value>
  </Binding>
</Bindings>

```

The value must be written in format that is understood by type of the property.

Examples:

Type	Value
Color	"[r,g,b,a]" for a single color or "r1 g1 b1 r2 g2 b2 r3 g3 b3" for matrix syntax. All numbers are in range <0, 1>
Enum	See Tool Reference chapter for possible values for all properties. Generally it is equal to content of the enum editor.
File	Relative path to the Tool directory.
Vectors	"[x,y]" where x, y have correct type (Integer/Float). You can guess the type of the property from the editor.
Boolean	Both "true"/"false" and "1"/"0" notations are supported.

Multiple values to one binding

It is possible to bind multiple values to one binding, where different data points can be added to one Tag for example. The values are separated by string properties. For instance if binding to NFL Zebra data for PathPlayerNumber and PathPlayerLastName within a tag, you can set the following formatting:

```
#${(PathPlayerNumber)} . ${(PathPlayerLastName)}
```

This would result in the tag being populated as per the picture example below.



Generic XML Data Binding

Using the XMLDataBinding plugin, it is possible to watch single or multiple files such as .xml or .csv for changes or modifications and transform them into the values.xml using an .xsl transformation file.

```
<xsl:stylesheet version="1.0"
xmlns:xsl="http://www.w3.org/1999/XSL/Transform">
<xsl:output method="xml" encoding="UTF-8" indent="yes"/>

<xsl:template match="/Root">
<Bindings version="1">
<Binding name="Binding">
<xsl:for-each select="XmlFile/XML/*[starts-with(name(), 'PLAYER')]">
<xsl:variable name="id" select="ID"/>
<Value>
<xsl:attribute name="heading"><xsl:value-of
select="/Root/CsvFile/CsvFile/Line/Value[1] [@value =
$id]/../Value[2] /@value"/></xsl:attribute>
<xsl:value-of select="value(DATA)"/> </Value>
</xsl:for-each>
</Binding>
<Binding name="Data">
<xsl:for-each select="XmlFile/XML/*[starts-with(name(), 'PLAYER')]">
<xsl:variable name="id" select="ID"/>
<Value>
<xsl:attribute name="heading"><xsl:value-of
select="/Root/CsvFile/CsvFile/Line/Value[1] [@value =
$id]/../Value[2] /@value"/></xsl:attribute>
<xsl:value-of select="value(DATA2)"/> </Value>
</xsl:for-each>
</Binding>
</Bindings>
</xsl:template>
</xsl:stylesheet>
```

Binding to Opta feed

Opta provides several data feeds with information from a wide variety of competitions across the world. Currently we support F40 Squad Feed which contains information on each team's registered playing squad for a given competition.

To be able to use data you need an account at Opta with subscription to desired competitions. For more information about provided data and authorized resellers please visit: <http://www.optasports.com>

Using Opta data within Paint is a licensed feature.


Configuration

In the config editor, go to the Plugins tab and list the **TeamBindingOpta** plugin and enable it. Paste the URL of the feed to the corresponding field. The URL is provided by Opta's resellers and contains feed specification, competition, season, username and password. You can specify the suffix for binding names provided by the Opta module which might help to prevent name collisions and orientation in the Bindings dialog.

Value updates

The binding points can be fed with team names and player names. First you have to specify the teams for which the data will be loaded.

1. Open the Administration menu on the Clear button
2. Choose Opta binding.
3. The team selection dialog will be shown and desired feed will be downloaded.
4. The application caches the feed data, you have to hit the Refresh button to download it again.
5. Select the teams and click the OK button.
6. Now the binding points are fed with available values.



See the "Value updates" section for information on how to assign particular value to a tool property.

Binding to GSIS Data

GSIS provides information and statistics about NFL games. It's possible to download the game data and use it as binding values within Paint.

We support importing Gamebook data in .xml format. The file can be downloaded at <http://nflgsis.com/>. Each Gamebook file contains data for one NFL game.

GSIS data within Paint is a licensed feature.

Configuration

In the config editor, go to the Plugins tab, list the **TeamBindingGSIS** plugin and enable it. You can specify suffix for binding names provided by the GSIS module which might help to prevent name collisions and orientation in the Bindings dialog.

Start using Gamebook

Download the gamebook for the game you are interested in. You can download several gamebooks and change active gamebook file during runtime (this is useful for analysis of multiple games).

Invoke popup menu on the Clear button, choose 'GSIS binding' menu item and browse the gamebook file. Now the binding points are fed with new values read from the Gamebook.

See the "Value updates" chapter for information on how to assign particular value to a tool property.

See the Connecting to a binding point" section for a list of all supported binding names in the All available binding dialog.

Binding to Tracab Player Path

Clips imported from ChyronHego Virtual Placement might contain Tracab data (player paths, names etc.) All data from the Tracab players xml file such (player name, jersey number etc.) are held as Path metadata and can be used as binding value.

For example: You'd like to create a Tag drawing (that follows the player path) with the player name. Bind TextValue property of the Tag tool to PathPlayerLastName binding point. Link the drawing animation to the player path. Text of the tag is automatically resolved to contain the player's name.

See the "Linked keyframe animations" section for more info.

Opta's SDAPI Event Data

Opta's Sports Data API (SDAPI) allows users with an Opta OAUTH key to access a live push feed of event data from Opta and sync it to Paint's record train. This can be set up in the EventLogging section of the plugins tab of the Configuration Editor. You are able to click on events which will take you to the point of the event in the timecode. It is also possible to search for and filter events.

You can also preview upcoming fixtures and offset data and video in order to synchronize the two, if they are out of time.

Controls

- Fixture – Allows you to select your fixture of choice from those available.
- Reconnect – Reconnects to the data feed.
- Time Correction – Allows you to set a time correction between the video and data, in milliseconds.
- Preroll – Sets a preroll time before events.
- Search – Allows you to search through the events that have been logged for the game.
- Export All – Exports the events to XML.
- Close – Closes the dialogue.

09: Formation Tool

Overview

The formation tool is designed to convey tactical insight of the game to viewers or players. The video preview is replaced with pitch background and the formation graphics, which usually consists of counters for one or two teams. The counters are able to be moved and combined with other Paint Tools to further explain tactical points. The tool allows you to prepare several game setups and present them later.



Formations

The formation plugin is disabled by default. You can enable the plugin in the Config editor, Plugins tab.

Formation setup panel

The Formation tool setup panel is accessible via the Formations widget by clicking the "Formation Tool Setup" button. Clicking it again will then hide it.

The setup panel consists of following sections:

- Formation Tool widget
- Preset setup
- Top preview
- Counters setup

Formation tool widget



The widget allows you to control the Formation tool and navigate over the presets. You can invoke a popup with a list of available presets on the widget and select one of them.

Button	Description
	Shows/Hides the Formation tool
	Shows/Hides the Formation tool setup panel
	Selects previous/next preset
	Reloads the currently selected preset. All counters return to their position defined in the underlying formation
	<p>Saves current state of current preset.</p> <ul style="list-style-type: none"> Save - overrides current preset. Save As - creates a new preset with a chosen name. Send to clip - saves preset as a clip in bank at chosen position.
4-3-3 LIVERPOOL	Name of the currently selected preset. Clicking will bring a selection popup. Presets can be reordered by dragging the handle on the left or removed by clicking the bin button.

Note: The Formation tool Requires a license upgrade.

Formations tab

Here you can view and edit formations used within the tool. You can also create formations.

- Controls (New): Creates a new formation with default counter positions.
- Clone: Clones the currently selected formation.
- Remove: Removes the currently selected formation. A formation used in a Preset cannot be removed, you have to remove the preset first.
- Team dropdown: Allows you to access data naming feeds by Binding to Opta feed or Binding to GSIS data.
- Player table: Allows you to add additional information to the Counters such as Player name, jersey number, set x, y co-ordinates for counters and set individual images for counters. You can invoke popup menu for given and choose player name from the list of bindings. Counter Id's serve for pairing of table row with counter in the Formation preview only.
- Formation preview: See the counters and their position on the pitch. You can drag and drop the counters on desired positions.



Add a player

1. Right click in the Formation preview at the position, where the new players should appear.
2. Choose **Add** from the popup menu.

Remove a player

1. Right click on the player to be removed.
2. Choose **Remove**.

To be able to use Opta/GSIS bindings in the Player table, the Opta/GSIS modules must be running and providing data. See more information in the corresponding chapters.

Presets


Presets tab

In the first instance it is important to note that a preset differs from a formation. A preset is a saved amalgamation of information such as a team texture plus the ability to show more than one team within the tool in the preview window.

Control

- **New** – Creates a new Preset with default counter parameters.
- **Clone** – Clones the currently selected preset.
- **Remove** – Removes the currently selected preset.

- **Preset list** – Displays a list of the available presets. Change the preset selection to view/edit preset parameters.
- **PitchView dropdown** – Allows you to select one of the predefined pitch view angles for currently selected preset.
- **BackgroundCameradropdown** – Allows you to select any incoming video feed as a background source for the formation.
- **Presetpropertiespanel** – Allows you to edit counter textures, effects or assign a formation to both teams. To immediately see how property changes are applied to formation appearance, it is recommended to show the formation using the Formations widget before editing properties.



Preset setup

In this section you can find configuration of HOME and AWAY teams in preset.


- **Home Team / Away Team:** Team switch, indicates which team is displayed and edited below. Checkboxes right next to them control whether or not the team is active and its players should be displayed in the preview.
- **Squad import:** Allows you to access data naming feeds by Binding to Opta feed or Binding to GSIS data.
- **Pitch view:** Allows you to select one of the predefined pitch view angles.
- **Texture file, Scale:** Default values for player texture and its scale factor. Separate for each team.
- **Glow effect:** Glow texture shown below players in the preview when they are selected. Can be turned off by the checkbox.
- **Formation:** Formation defines the positions of players in a team. Last used formation is displayed, selecting a different one will apply it, moving all players in the team. Existing formations can be removed, new ones can be created by manually moving the players to desired positions, then clicking on the save button and choosing name. Separate for each team.
- **Pitch grid:** Show/hide pitch wireframe overlay over the background in the pitch window

Top preview

A simplified preview of the pitch with current position of players (counters). Currently unused players are placed in the bottom "Unused counters" section.

Players can be:

- Selected by left clicking on them
- Moved by dragging
- Removed by right clicking and choosing the "Remove" option
- Added by right clicking anywhere on the pitch and choosing the "Add" option



Formation preset as clip

After a preset is sent to a clip via the option in the Formation Tool widget, a basic 25s clip with the preset background and Counters is created. The preset in the clip is a current state copy of the preset in the Formation model.

Counters now behave as standard drawings and therefore can be viewed and managed in the timeline (only exception being they cannot be deleted). They inherit all properties from the origin preset counters and their production is defined across the whole clip.

The clip can then be managed (rename/move/delete...) and used (add/remove/edit tool drawings) same as any other clip.

Keyframing counter positions

Position and production timing of Counters can be adjusted in the same way as for tool drawings by first switching to the Edit mode and then changing position at required times. This will create position keyframes for affected Counters and defined paths will be showcased with lines.



Changes then need to be saved by clicking the Save (modified) button.



Adjusting in/out points

The size of the preset clip can be adjusted in the In/Out point widget by jogging to required time and marking a new in/out point (click and hold for 1s).



Counter Setup

Here is the configuration of the currently selected player. You can edit texts, precise position and override counter texture and/or its scale.



Text style

The top header controls the style of currently selected text (highlighted by green).

Text style is shared across all players from the team.

- Show/Hide text
- Position of text relative to the player
 - By precise X and Y coordinates
 - By the virtual joystick
 - Left click to activate (joystick will turn to green)
 1. Move the text
 2. Hold and drag the joystick by mouse

3. Use arrow keys
4. Scroll over the joystick (scroll = Y coord, scroll + SHIFT = X coord)
5. Click anywhere else to deactivate

Text font - family, horizontal align, size, bold/italic modifiers and color

Text values and position

In the bottom left you can change text values of the currently selected player, remove existing text (from the whole team) by clicking the "-" button next to it or add new text (to the whole team) by clicking the "+" button below.

On the bottom right there is an advanced configuration of the selected player.

You can:

- Edit its position precisely by X and Y coordinates
- Override default team texture
 1. Click on the link button (white = linked to team, red = unlinked/overridden)
 2. Define custom player texture
- Override texture scale factor
 1. Click on the link button (white = linked to team, red = unlinked/overridden)
 2. Define custom texture scale factor

Text tab

Here you can set properties for text rendered over the counters in the video preview area. Unfortunately, most of the editors don't have 'Live update'. You have to hide and show the formation tool using the Formation Widget to see the changes in the video area.

Using your own counter textures

The tools come ready to use with default resources.

To add your own counter textures, copy them into:

Operating System	Location
Windows	Documents\Paint9\Formation\Soccer\Counters
macOS X	/Library/Application Support/ChyronHego/Paint/Formations/Soccer/Counters Replacing default textures is not recommended as they might be overwritten during the next installation process.


Note: The Formation tool requires a license upgrade

10: Importing Data

Tracab Data Import

Paint supports importing video clips and pairing them with player paths exported from Tracab systems. The paths allow you to link Keyframe animations to them.

See the keyframe animations section for more info.



Workflow

1. Get the match data from a Tracab system for the match of interest. The data consists of the player positions definition file (.dat) and match metadata file (.xml). These two files must be in the same directory.
2. Enable the TracabData plugin in the Config editor, Plugins tab.
3. Import a clip from the match of interest and define 3D perspective (see 3D Calibration).
4. Open the Administration menu on the Clear button and choose “Import Tracking Data > Import Tracab data”.
5. In the import dialog Browse the .dat file to import the data.
6. Match the current video with the correct time in the players data.
7. When the import is finished, click on four players in the video (click on their feet, not body - see example below).
8. In most cases, four players are enough to find the match. If the found match is ambiguous, you will be asked to click on another player. If no match is found, press the Clear button and start again. We recommend clicking on different players.
9. When a match is found, but computed positions differ from players' real position slightly, use the slider at the bottom part of the Import dialog. It allows you to display the players' positions from the timeframe of the computed time match. Leave the slider at the time of the best match.
10. Press Save to save the paths to the clip.
11. You can import the data into another clip or close the dialog and start binding tools to the newly imported paths.



Note: Tracab data import requires a license upgrade.

Zebra NFL Data Import

Zebra NFL Data Import plugin allows to import player tracking data from NFL NGS servers. Imported data can be matched with Paint clips in the same fashion as Tracab data.

Workflow

1. Acquire NFL NGS tracking data login credentials from NFL.
2. Enable ZebraData plugin in Config Editor, Plugins tab. Type login credentials into the plugin configuration fields. Save configuration and launch Paint.
3. Import a clip from the match of interest and define 3D perspective (see 3D Calibration).
4. Open the Administration menu on the Clear button and choose “Import Tracking Data > Import Zebra NFL data”.
5. Use Download Zebra NFL Data button to open Download Dialog. 
6. Download Dialog allows user to choose a season and a particular game for download. To narrow down list of games available, it is possible to filter game list using the Search field. Data to be downloaded can be trimmed down to specified time range by entering game time values into the Start Game Time/ End Game Time fields.
7. After selecting the game, use Download button to start downloading game data from NFL NGS servers.
8. After the download finishes, data are ready for matching against video.
9. To narrow down the number of NFL plays where the matching algorithm searches for match, use filtering.
10. After setting filtering criteria, apply the filter by pressing Filter button. For actual matching of players, use the same workflow as with the Tracab data.

Selecting the Player Data checkbox in the ZebraData section of the Configuration Editor Plugins tab enables player names to be automatically bound to imported targets to PathPlayerNumber or PathPlayerLastName. You can then link tags, labels or animations to the player path (see Linked keyframe animations chapter).

Note: Zebra NFL data import requires a license upgrade.

11: 3D Pitch

Overview

Paint allows the possibility to use 3D tools and import Tracab data. First you have to use the Calibration editor to set the 3D perspective.

3D Calibration Editor

The calibration editor is available when a clip is selected. When the perspective is successfully set, it is saved into the clip and recalled together with the clip. Video frames, in which the perspective has been defined, will be referred to as keyframes. Perspective in non-keyframe video frames is computed from the surrounding keyframes.

Calibration editor buttons

Button	Description
	Default state. The calibration editor is not active. No perspective has been set for the current clip. Click the button to enter the calibration editor.
	The calibration editor is active. You can setup the perspective or see tracking results. Click the button to save the current perspective and leave the calibration editor.
	Perspective has been set and tracking is good. The calibration editor is not active. Click the button to enter the calibration editor.
	Calibration is disabled. This usually means that no clip is selected.
	Rotate Calibration Wireframe

Note: 3D pitch features require a license upgrade.

Pitch type selection

There are several predefined supported pitch types. Pitch type selection is available in the popup menu invoked for the Calibration editor button. The popup cannot be invoked when the Calibration editor is active.


Manually changing pitch type while the currently selected clip has been calibrated causes all calibration data in the clip to be reset.



Perspective definition

Select a clip and press the Calibration editor button. The wireframe of the selected pitch appears in the video preview. The wireframe contains draggable points which can have three states:

State	Description
	Default state. The point is ready to be set.
	The point cannot be set. This happens when there are two other points already set that form a line with this point.
	The point has been set.



Drag a point of the model and drop it on its position in the video. Drag another point until the rendered pitch fits the pitch in the video. You need at least **four** points to be defined for the first keyframe in the clip and at least **two** points for all additional keyframes. Until the keyframe is defined the video is blocked at the frame the first point was dragged.

Image Description: In the picture below, you can see a nicely added perspective. You can see the near side line doesn't fit perfectly, this is caused by lens distortion. The 3D features will work fine with a calibration like this. Lens distortion will be calculated and applied when two or more calibration frames exist.



Now jog through the video sequence in which you would like to use the 3D features. If the calibration starts to drift away, fix it by defining another keyframe.

When done, press the Calibration editor button which saves the calibration to the clip.

When a point is placed on the wrong position in the video, you can use the Undo button to undo the last edit or Clear button to clear keyframe.

Occasionally, it could be the case that the computed perspective is wrong. In this case just define another point in the current keyframe. When the computed perspective doesn't allow you to define another point (examples: all points are projected beyond the screen boundary), press and hold the CTRL key (which causes the pitch to be rendered in default projection while the key is down) and define the point. If this doesn't help, press the Clear button and start the keyframe again.

For calibration of behind-goal camera angles you can rotate the pitch wireframe by calling the RotateWireframe action.

Using Paint tools with the 3D pitch

Some tools, like the 3D arrow and the Column tool, are inherently dependent on an existing pitch calibration. Many tools support both on-screen and on-pitch use.

For control over placement of tool graphics, tools have a 3D Scale property.

- With 3D Scale disabled, on-screen graphics are created.
- With 3D Scale enabled and a valid pitch calibration, the tool creates on-pitch graphics. The 3D Scale value controls the relationship between on-screen and on-pitch size of the graphics.

3D and 2D tools distinction


Based on their ability to be used on-pitch or on-screen, tools are visually differentiated by a small cube icon in the top left corner (when using default skin) once placed into the toolbar.

Tool Icon	Description
	A white cube represents tools that strictly require a calibrated pitch. Such tools can only be used with a valid pitch calibration.
	A gray cube indicates tools suitable for both on-screen and on-pitch use. These tools have 3D Scale enabled and act like 3D tools on clips with a calibration and like 2D tools on clips without it.
	Tools that are not marked by any cube icon either cannot be used on-pitch or they have 3D Scale disabled.

3D tools without 3D pitch

In different scenarios, you can be presented with a floating message at the top of the preview. The message can be of an informational, warning or error character and it may also contain a clickable action.

Image description: If you attempt to place a 3D tool into a clip without pitch calibration, an error message appears providing a possibility to quickly activate the calibration editor.




Pitch Auto-Calibration

The Pitch Auto-Calibration plugin is an additional licensed feature. The feature allows for automatic calibration of pitch within a clip. It creates several calibration frames throughout the clip in case the camera moves and the pitch position changes.

Workflow

When a clip is imported to the Paint the pitch calibration will automatically start running in the background once the import is finished. Calibration frames will start to appear from the beginning of the clip.

Progress of the background calibration is visualized by a progress bar over the clip. The clip can also be used normally during the calibration process.



Re-calibrate pitch

The calibration process can also be triggered manually by an action in the clip context menu. If you want to re-track players simply select the Calibrate Pitch option.

Important: Current calibration frames are overwritten!



Cancel

The calibration process can also be canceled by selecting the Cancel Calibration option in the clip context menu.



Limitations

macOS machines need to have version Big Sur or newer. The speed of the calibration process is dependent on system hardware. M1 Macs and PCs with strong GPUs will perform best. Currently not available for recorded clips with multiple inputs, only single input recordings or imported clips.

Note: Pitch Auto-Calibration requires a license upgrade.

12: 2D Player Tracking

2D Player Tracking plugin


Overview

The 2D Player Tracking plugin is an additional licensed feature. The feature allows for automatic keyframing of players within a clip. This creates paths for tracked targets, which can then have graphics linked to them. 2D player tracking does not require a chromakey or calibration to be set in order to be initialized.

Workflow

Step	UI
1. Ensure that your license is licensed for Tracking Data.	—
2. Enable the 2DPlayerTracking plugin in the plugins tab of the Config Editor.	—
3. To turn on the player tracking engine, select the player tracking icon.	
4. It will then turn red.	
5. Now, select the players in the video that you wish to track, this will add a green target to your selections.	
6. Press the tracking engine play button, this will turn	

7. In the Preview Window you will then see bounding boxes tracking your players of choice.



8. Once you are happy with the tracked paths, stop the tracking engine by pressing the pause icon.

9. Now reload your clip. The paths will be stored as keyframes.

To link a graphic to a path, select a keyframed tool, hit the link in the bottom left of the GUI and click inside the target. To turn graphics on and off, use Production Start/End.

Note: 2D Player Tracking requires a license upgrade.

Player Auto-Tracking

Overview

The Player Auto Tracking plugin is an additional licensed feature. The feature allows for automatic keyframing of players within a clip. This creates paths for tracked targets, which can then have graphics linked to them. It does not require a chromakey or calibration to be set in order to be initialized.

Note: Player Auto-Tracking requires a license upgrade.

Workflow

When a clip is imported to the Paint the player tracking will automatically start running in the background once the import is finished. Paths of players will start to be tracked from the beginning of the clip.

Progress of the background tracking is visualized by a progress bar over the clip. Both the clip and generated paths can also be used during the tracking process.



Re-track players

The tracking process can also be triggered manually by an action in the clip context menu. If you want to re-track players simply select the Track Players option.

Important: All existing player paths will be overwritten!



Track Players

Cancel

The tracking process can also be canceled by selecting the Cancel Tracking option in the clip context menu.



Cancel Tracking

Limitations

macOS machines need to have version Big Sur or newer. The speed of the calibration process is dependent on system hardware. M1 Macs and PCs with strong GPUs will perform best. Currently not available for recorded clips with multiple inputs, only single input recordings or imported clips.

After calibration is defined on a clip, the player paths need to be re-tracked to be converted as 3D

Note: Player Auto-Tracking requires a license upgrade.

13: Multi-Angle Telestration

Overview

Paint has the ability to synchronize clips with footage of the same game from multiple angles and then share 3D graphics between them. All clips need to have pitch calibration defined.

Clip Group Editor

To synchronize multiple clips you first need to create a clip group. It contains information about the synchronization frames and the shared drawings.

Manage clip groups

To create a new clip group or edit an existing clip group:

1. Choose the **Sync Clip** option inside the clip context menu.
2. An editor will appear over the tools panel showing the content of the clip group with the chosen clip. There will be a row for each clip with its name and the sync frame visualized as a timer and a screenshot.



Synchronization frame

Clicking on the clips will select it for the purpose of editing the sync frame. To change it first seek to the desired frame and confirm by clicking the button in the preview. Both timer and screenshot will update.



Add angle

1. Click Add Angle.
2. All usable clips in the bank will start blinking.
3. Clip on one of them to add it or press ESC to cancel operation. Clips that are already in a different group cannot be added.

Remove angle

Each clip row has a bin button for removal from the group. Removing the last clip will result in group deletion and loss of its synchronized drawings.

Existing drawings

Clips added to the group can already have some drawings in them. Whether or not they will be converted to synchronized is set by the checkbox in the bottom right.


Exit editor

- Ok = Saves the current group state and closes the editor.
- Cancel = Reverts the group to the previous state before editing and closes the editor.
- Selecting another clip in the bank = Loads its group into the editor (if the selected clip is/can be synchronized just close the editor) if the selected clip cannot be synchronized.

If some changes were made in the current group a confirmation dialog will ask whether you want to save them.

Visualization

For clarity, both synchronized clips and drawings are marked with this camera icon.



Synchronized drawings

Synchronized drawings are inside the clip group and will be visible in its clips.

There are two ways to create synchronized drawings.

- Create a regular 3D drawing inside one of the synchronized clips and click save.
- Add a clip which contains some drawings as a new angle.

Switching angles

When inside a synchronized clip use "PreviousAngle" and "NextAngle" actions to cycle through the angles in one way or the other.

Current time and playback speed is maintained during the switch.

By default these actions are bound to:

- Win: CTRL + SHIFT + LEFT/RIGHT
- Mac: CMD + SHIFT + LEFT/RIGHT

Limitations

The accuracy of multi-angle telestration depends completely on 3D pitch calibration. Therefore, if one clip is recorded from a difficult angle and the automatic calibration doesn't produce accurate enough result, the drawings of other clips in such a clip will appear shifted and vice versa.

For such clips, users can edit or define the calibration manually though the Calibration Editor.

Note: Multi-angle telestration requires a 3D tools license.

14: Chroma Key

Overview

Paint comes with a built-in chroma keyer. There are two types for keyers, Adaptive and Gauss. The type of the keyer can be set in the Config editor, User Interface tab.

Adaptive

The Adaptive keyer is only used in a Paint Live configuration (although it can use the Gauss keyer too). Using the Adaptive keyer in recorded cameras is not supported.

The Adaptive keyer is fully automatic. An initial key is computed when the application is started. Then the algorithm maintains and adapts the key as the match continues and the light conditions change.

You can check the current key at any time. Just open the Chroma Key Editor and choose Mask or Preview mode. All other functions in the editor will be disabled.

Gauss (manual)

This type of keyer is fully user-operated. Open the Chroma Key Editor and pick the colors you want to be part of the key.

Chroma Key Editor

The editor is accessible from the Administration menu on the Clear button. Open the popup using a right mouse button click and select "Edit Chromakey". Dialog with chroma key controls appears:



The dialog contains several buttons:

- **Reset:** Removes the current chroma key.
- **Undo:** Restores to the state before the very last pick in the preview.
- **Originalvideo:** No chroma key visualization. In this option you see the state before activation of the chroma key dialog. If there are any drawings, they are visible. This is useful to see the graphics with current key.
- **Mask:** Shows only the mask. The mask is black-and-white image. When the key is correctly set, you will see a white pitch with sharp black pitch lines and outlines of the players.
- **Preview:** This is a mix of mask and the original video. You can see the input video and preview of the mask.

The mouse cursor changes to a square defining the area, from which the chroma key is computed.

Select the area in the video to be keyed. Repeat this step until the mask fits. The mask should look like:



Adjust the size of the pick area

Use the Pick size slider in the Chroma key dialog to adjust the size of the pick area. Alternatively, you can use **CTRL + mouse wheel** to change picker size.

Automatic refinement

Each time you create a new drawing, a new sample of the chroma key is taken and added to the current key. Only samples that don't cause significant changes to current key are taken into account. All refinements are discarded:

- When the Chroma key editor is opened
- When the Clear button is pressed

Automatic key refinement can be enabled/disabled by check box in the Chroma key editor. The value is saved and used next time the application is launched.

Automatic refinement is available only when Live input is selected.

Automatic (adaptive) Keyer

If Adaptive keyer has been enabled in the Config Editor, the Chromakey editor will only show the key that has been placed automatically, it is not possible for you to add or remove Chroma when Adaptive keyer is enabled.

Chroma key stored in a clip


Each clip can have its own chroma key, which will be loaded when the clip is selected and unloaded when the clip is deselected. The stored key can be deleted or redefined later.

When a new clip is created, the current chroma key setting from Live cameras is copied and saved with the clip. Clips with no stored key inherit their key from the Live input. A stored key can be redefined. Just select the clip, open the chroma key editor and redefine the key.

A chroma key stored in a clip can be deleted. Select the clip, open the chroma key editor and press 'Clear'. From then, chroma key for the clip is inherited from the Live input again.

Tools using chroma keyer

Most tools support the chroma keyer. You can change the keyer settings in the popup invoked for a tool.




Setting	Description
On	The tool is keyed.
Off	The tool is not keyed.
Shadow only	The tool is not keyed but its shadow is keyed. Shadow must be enabled on the tool to make this choice available.

15: Keyframe Animation

Overview

Most tools support animations. Once the animation is created, it can be stored in a clip and played together with the clip. Define the position and size of a tool drawing in several keyframes (time points), position and size between the keyframes is automatically interpolated.



Basics

Create new animation

1. Select a clip.
2. Select a tool to animate and place drawing into preview.
3. Define the position of the drawing at several time points (drag drawing to the desired position).
4. Size can be changed by mouse wheel while holding a Ctrl key.
5. Save the animation into a clip

Edit existing animation

1. Select a clip with a stored animation.
2. Press the Edit button.
3. Adjust the animation and save it to the clip.

Remove existing animation

1. Select a clip with a stored animation.
2. Press the Edit button.
3. Press the Clear button.
4. Press the Save button.

Controls

Control	Description
	Keyframe
	Hovered keyframe Click it to move to the time of keyframe
	Active keyframe
	Delete actual keyframe
	Enable keyframe visualization
	Disable keyframe visualization

Linked Keyframe Animations

Paths

Paths allow you to create one-click animations from an existing path:

- Each existing Keyframe animation represents a path.
- Clips imported from Virtual Placement 7 with Tracab are capable to carry paths of all players.

Bind tool to a path

Each path represents a position animation that can be used to animate another drawings. Several drawings can be bound to one path.

1. Select a clip that contains paths.
2. Select the tool you would like to bind to a path.
3. Press the Bind button. (see image below)
4. Select one of the paths.



Only tools with motion tracking ON can be bound to Paths created by a motion tracked tool. Paths that cannot be used by the selected tool are not displayed.

Delete drawing bound to a path

Use Graphic Eraser to delete drawings.

Change offset from the path

You can change the offset of the drawing from the path. The drawing will animate on the path but will keep a fixed offset from it.

Pick the drawing to be adjusted and place it on the desired offset from the path.

Edit existing path

The paths are editable. When a path is changed, the trajectory of all bound drawings is changed to follow the updated trajectory of the path.

Editing is implemented the same way as editing a keyframe animation.

Remove path

Removing paths is not supported.

Choose which paths are visible

In default state paths are visible and accessible at the same time. But when pitch calibration is defined a user can come across two types of paths:

- 2D = Defined in pixel coordinates directly on the screen.
- 3D = Defined in meters on the virtual pitch set by calibration.

To see only one type or the other simple use the Paths view button in the left top menu to rotate between these 3 views:

Display	Description
3D 2D	All paths
3D 2D	Only 2D
3D 2D	Only 3D

Shape a path

To adjust small imperfections in paths, coming from the Player Tracking processing or after using the Join/Swap tools below, the path shaping tool can be used.



To shape a path:

Step	Display
1. Enable Path Shaping tool by activating the Path Shape button. All existing paths get shown as circles for current player positions with a trail visualizing immediate previous and next movement.	
2. Click on any path manipulator to select it, visualize its whole trail and hide all other paths	
3. Jog the time where the path needs to be shaped.	
4. Drag and drop the path manipulator to a new desired position.	
5. Click on the path manipulator to go back to edit other paths (step 1) or repeat steps 3 and 4.	

Linked paths

If some paths are linked together for example with the Linked Cursor tool, all linked paths will act as one, meaning clicking on either one will select/deselect all of them, and will be visualized at the same time.



Smoothing

Path shaping tool also supports adjustable level of smoothing/propagation of the adjustments to the nearby times to control whether only the current position should be edited or a more realistic player movement is preferred (without spikes).

To adjust the smoothing level, hold the CTRL key (CMD on macOs) and scroll. The current level is visualized by a white highlight around the current keyframe.

Examples		
No smoothing. Only the current position is adjusted.		
Low smoothing.		
High smoothing.		

Extending paths

The Path Shaping tool can also be used to extend paths on either end.

To extend a path:

Step	Display
1. Jog outside its definition (before beginning or after end). This is visualized as a dashed manipulator at last known position.	
2. Drag and drop the path manipulator to a desired position.	
3. This will define a new keyframe at given position and current time and add it to the path.	


Swap paths

Another tool used most often to improve results of player tracker processing.

Allows to swap two paths crossing each other where at the crossing point, paths get swapped between players incorrectly.



To swap paths:

Step	Display
1. Enable Path Swap tool by activating the Path Swap button. Existing paths get shown.	
2. Jog in time a few frames after the incident. Click one of the two path manipulators to select the path. Its selection is visualized with a blue color.	
3. At the same frame, click the other manipulator to select the second path.	
4. After both paths are selected, they are swapped at the point of the crossing, or at the point where they are closest to each other, when they are not crossing directly.	

Split paths

Any path can also be split into two at required time. A typical use case for this is cutting off sections which otherwise would be difficult to shape into desired form. The missing section then can be filled by extending the "well-behaving" part via the Shaping tool.

To split a path:

Step	Display
1. Enable Path Split Tool by activating the Path Split button. Existing paths get shown.	
2. Jog to the time where you want the split to occur. Click the manipulator of the path that should be split.	
3. Path is now split into two and the first part (earlier in clip) stays selected and highlighted.	
4. Select the Shaping tool to edit/extend the first part or click the manipulator again to deselect the first part, jog forwards and select the second part	

Join paths

A typical scenario for Path Joining is connecting two distinct paths coming from the Player Tracking processing. Paths to be joined should not overlap in time. In case they are overlapping, the path that is starting first in time takes precedence.



To join two paths:


Step	Display
1. Enable Path Joining Tool by activating the Path Join button. Existing paths get shown.	
2. Jog to the 1st path time range. Click on the path manipulator to designate the first path for joining.	
3. Jog to the 2nd path time range. Click on the path manipulator to designate a second path for joining.	
4. Paths get joined.	

Graphic Eraser

You can selectively clear any graphics.


Erase the whole drawing

Press the Eraser button. A cross button is displayed at the end of graphic elements that belong to the currently selected tool. Press the cross control to erase the drawing.



Erase one keyframe

Enable keyframe visualization. Press the small eraser button to delete the current keyframe only. The button is available only when a keyframe is selected.



16: Sweep Calibration

Sweep Calibration (Live Inputs)

In Paint 10 you can use the game cameras in soccer Left Offside, Main, Right Offside (But not limited to having all three cameras) to create a calibration before the game by using the new function inside the UI called sweep calibration (blue highlighted tool)



Feature needs to be turned on inside Paint config under the plugins tab and is a licensed feature. The Plugin also allows you to load an existing Virtual Placement calibration and use it inside of Paint.



Calibration process

- Calibration works for three cameras (Left Offside, Main, Right Offside) - NFL and NCAA Football added to 10.1 with 3 game cameras included.
- Perform a sweep from left to right or vice versa on one camera at a time together with the camera operator while inside the sweep calibration. The camera operator needs to be as zoomed in as possible but needs to see all the lines of the pitch during the sweep for the best result.
- Select the camera you want to calibrate in the UI, in this case left, game or offside left.



- Sweep is saved inside the recorded footage and the operator can go back and forward within the video using a shuttle or UI to mark the different lines during the sweep process.
- Stop the video 4 five times during the sweep provided by the camera operator and give the system reference of 4 point in each specific stop two times on the left side of the pitch and two on the right side (make sure the stops cover left to right of the field in general)
- Once done press the calibration button inside the UI and move to the next camera.

Note: Sweep Calibration requires a license upgrade.

ABOUT US

Chyron is ushering in the next generation of storytelling in the digital age. Founded in 1966, the company pioneered broadcast titling and graphics systems. With a strong foundation built on over 50 years of innovation and efficiency, the name Chyron is synonymous with broadcast graphics. Chyron continues that legacy as a global leader focused on customer-centric broadcast solutions. Today, the company offers production professionals the industry's most comprehensive software portfolio for designing, sharing, and playing live graphics to air with ease. Chyron products are increasingly deployed to empower OTA & OTT workflows and deliver richer, more immersive experiences for audiences and sports fans in the arena, at home, or on the go.

CONTACT SALES

EMEA • North America • Latin America • Asia/Pacific
+1.631.845.2000 • sales@chyron.com

